

# **IMPORTANT**

## ***Installation Instructions for EMIGMA Basic Version***

**To uninstall EMIGMA Basic, use “Control Panel” -> “Add/Remove Programs”**

Run Emigma\_Basic\_setup.exe and follow the instructions of the setup program.

***Special Instructions for Windows 2000, Windows XP and Windows Vista Users:***

***--- The installer must have administrative privileges.***

***After installation it is recommended to check the following environment variables:***

- 1) Set an environmental variable through “Control Panel” -> “System”  
SET environmental variable: e.g. TGS\_LICENSE\_FILE  
to  
“c:\Program Files\Emigma\_Basic\bin\password.dat

- 2) Add the “\bin” to your path:  
e.g. “c:\Program Files\Emigma\_Basic \bin

***Note: If you have installed EMIGMA BASIC into a directory other than “c:\Program Files” ensure that you use that path in the above 2 steps.***

**Re-boot** your computer.

---

Note:

1. During the installation, setup will automatically create a directory “C:\Preikon” if this directory can’t be found. This directory will sometimes be used to store special intermediate files. After installation please make sure the attribute of “C:\Preikon” is not “Read Only”. If setup fails to create “C:\Preikon”, please create it manually.

2. You will encounter a warning message when using EMIGMA Basic ‘TGS License File Error’. This is only a warning message. Please click OK to this message and continue normal use.

**Please contact us if you have any questions :Support Department, PetRosEiKon**

**Tel: 1 (905)-796-0324 Email: support@petroseikon.com**